

Q1 2021 CLICKSHARE SOFTWARE RELEASES

Channel briefing webinar

20 April, 2021



A Q1 RELEASE PACKED WITH NOVELTIES



Continued Quality Assurance

Continued focus on solving issues reported through service



Blackboarding & annotation Delivering blackboarding & annotation for our CX-30 and CX-50



Update and service your Logitech Rally through CX



Camera & microphone icons on wallpaper, active mute when red

Audit logs in XMS cloud

Enhanced traceability: every user action visible in Audit menu

Share how you want

Miracast on full CX-series

Mobile device audio sharing

Share the audio from your mobile device in sync with the video

Room availability

See the room availability on the ClickShare wallpaper (Office 365 only!)

CX-50 improvements

Improved latency on touchback AV sync improvements

ISO 27k for XMS cloud

Certified to deliver the most secure cloud management system

Remote sharing of room display ready to share in your UC&C app

The local room view is always

App-based conferencing

Enjoy wireless conferencing with the Desktop App [in beta]

Network integration For both the Button and the Base Unit

& Wireless client mode available

Airplay presence detection

Airplay connectivity possible through built in Bluetooth discovery

SmartCare information

Now available both on the ClickShare Configurator as well as XMS Cloud

More peripherals Support for additional peripherals

True 720p for Poly Studio & Bose VB1





The ClickShare Experience Great things happen when people click

Simple. Easy. Wireless.



App-based conferencing



Mobile device audio sharing



Screen sharing via Miracast



Annotation & Blackboarding



Remote sharing of the room display from within your UC&C



Room availability



Broadest range of peripherals



Network integration

Enterprise Grade



ISO 27001 for XMS



XMS Audit logs



Q1 SOFTWARE RELEASE KEY MESSAGES FOR MEETING USER

App or Button. Your choice.

Wireless Conferencing via App and Button

Better engagement

Meeting room status display | blackboarding & annotation

Share what happens in the room

Share contents from the in-room display with remote participants





Q1 SOFTWARE RELEASE KEY MESSAGES IT ADMIN

App or Button. The power of choice

Wireless Conferencing via App and Button

GoogleCast, Miracast & Airplay

Full BYOD support for screen sharing

Supports widest range of USB conference cams

The largest number of validated conference peripherals

Compatible with your network configuration

Multiple network integration options





April 20th

The ClickShare Experience Great things happen when people click

Simple. Easy. Wireless



App-based Conferencing



Mobile device audio sharing



Screen sharing via Miracast



Annotation & Blackboarding



Remote sharing of the room display from within your UC&C



Room availability



Broadest range of peripherals



Network integration

Enterprise Grade



ISO 27001 for XMS




XMS Audit logs



APP-BASED CONFERENCING



Join the call from your laptop.



Walk into the meeting room.

Share





Q



APP-BASED CONFERENCING


Wireless Conferencing with or without the Button

Installation

- Requires ClickShare Base Unit firmware v2.8
- PC Drivers available through separate download
 - Registration required for download
 - Admin rights needed for installation on pc
 - Mass deployment supported (MSI installer)
- Most recent version of the desktop app

Connect and meet

- 1. Connect to the meeting room
- 2. Meeting room peripherals created as connected devices
- 3. Use the meeting room camera and speakerphone in your conference call





APP-BASED CONFERENCING

Wireless Conferencing with or without the Button

- Windows 10 only during Beta, MAC support coming soon
- Mute-sync not available in Beta
- Network connected Base Unit
 - Base Unit must be LAN connected and PC must connect over the network
 - To allow for internet connection for video call
- Corporate network requirements:
 - Bandwith of up to 30Mbs per connection
 - Low latency (<50ms E-2-E)






SHARE WHAT HAPPENS IN THE ROOM WITH REMOTE PARTICIPANTS

Simplified user experience to share the room display remotely

by simply selecting it in your UC&C tool



No need to open the local view window, no need to create a second display on your system,

Room Display window is there when you need it



SIMPLIFIED SHARING OF THE LOCAL ROOM VIEW

View room display window always available in the UC&C app

- Connect to the Base Unit (CX)
- First Window when sharing in Teams/Zoom/...
- Button and App

The window is **not visible** on your computer

- No "tunnel vision"
- Border around the primary screen to indicate you're sharing








FLUENT VIDEO AND AUDIO SHARING FROM YOUR MOBILE DEVICE

Share the audio of your video to the meeting room in sync with the video

Greatly improves the experience when sharing recordings or online video's






LONG PRESS TO TAKE OVER THE SCREEN


Take over the whole meeting room screen with a long press

Tap the sharing button to add your content, hold the button to take over





BETTER ENGAGEMENT WITH ANNOTATION AND BLACKBOARDING



Switch between presentation view and the **blackboard** with one click

Snap and draw with the **annotation** functionality

Distribute your ideas via a **one-click save** to all connected apps



MEET WITH CONFIDENCE

- Confidence when starting your call status icons indicate whether the conferencing peripherals are available and when they are being used
- Mute icon on wallpaper with active mute ensuring peace of mind
- Know when someone is watching the meeting room screen with **local view**









Microphone actively muted

17



'ONE CLICK SYNC' IMPROVEMENTS FOR THE CX-50

An end-to-end latency reduction of 25-30% on the CX-50 improving both the **touch back** experience as the **AV sync during a call**.



The ClickShare Experience Great things happen when people click

Simple. Easy. Wireless



App-based conferencing



Mobile device audio sharing



Screen sharing via Miracast



Annotation & Blackboarding



Remote sharing of the room display from within your UC&C



Room availability



Broadest range of peripherals



Network integration

Enterprise Grade



ISO 27001 for XMS



XMS Audit logs



SUPPORTING THE WIDEST RANGE OF CONFERENCE PERIPHERALS: ADDITIONAL PERIPHERALS AND IMPROVEMENTS

- **New and fixed peripherals**: Nureva HDL200, Poly Eagle Eye Cube, AMX AVC-5100, Aver VB342, Aver VB342+, Poly Studio X30 and X50 and many more.
 - Firmware is currently with partners, 160+ devices have been validated so far with the 2.8 release. Final list can be found on the website: www.barco.com/clickshare/alliance-partners/peripherals. This list will be updated after the official release
- True 720p: some cameras did not send 720p when requested, this is now fixed
 e.g. Bose VB1, Poly Studio USB, Logitech Group, ...
- Peripherals are not active when not used by end-user,
 as a result, the LED (or other indication) will be off when not used



ALLIANCE PARTNER STATUS - APRIL'21

Please note that partner status might not apply to all of the alliance partners' products.





((KONFTEL logitech



Approved









Onboarding





















biamp. ClearOne. CTOUCH®



































StarLeaf **Symetrix**















MEETING ROOM STATUS DISPLAY: VIEW ROOM AVAILABILITY

Immediate overview of the meeting room booking,

ideal for huddle spaces and comfort cruisers








Only $\underline{\text{O365 room accounts}}$ are supported at this moment. Configuration can be done in XMS cloud only.

Available in XMS cloud as of mid May



VIEW ROOM AVAILABILITY: HOW TO CONFIGURE

In XMS cloud, go to the Calendar tab and press the Connect Button




Available in XMS cloud as of mid May



VIEW ROOM AVAILABILITY: HOW TO CONFIGURE

Log in with your O365 account and the meeting room accounts will show up on the left side, where they can be linked to Base Units.






MIRACAST SUPPORT ON CX-20 AND CX-30



Share your way! Now also on the CX-20 and CX-30 with additional Miracast support

To enable Miracast over Wi-Fi direct, disable the access point of the CX-20 or CX-30 and turn on 'Miracast' in the services page.

This will disable the access point and requires Buttons to be integrated into the network.




We aim to support Miracast Over the Infrastructure and Miracast with the Base Unit's access point turned on by the Q2 Firmware release.



BLUETOOTH PRESENCE DETECTION FOR AIRPLAY

Bluetooth Airplay discovery for easy Airplay discovery, regardless of network setup



However: Base Unit will only be shown on the laptop/iPhone if the device can set up a network connection to the Base Unit!

Already available on the CSE range, now also available on the CX products.



WIRELESS CLIENT AND DUAL NETWORK CONNECTIVITY



Set up wireless connection to your Base Unit for management




Enable BYOD for guests and employees, without losing internet connectivity

- Not advised to run Wireless Conferencing through the network!
- **Highly secured**, no bridging or pass-through
- **Dual network support** to deliver the best BYOD experience to both employees and guests
- CX-50 can support direct Button connections in a dual network setup
- Support for DFS channels with client mode on the Base Unit




CONCURRENT CONNECTIVITY MAKES THE CX-50 THE IDEAL DEVICE FOR NETWORK INTEGRATION

CX-50: concurrent connectivity



When in dual network setup or client mode, **Buttons can connect directly to the Base Unit** for maximum performance and best user experience for Wireless Conferencing.

CX-20/CX-30: no concurrent connectivity



When in dual network setup or client mode, **Buttons** must be integrated into the corporate network, a setup which is (currently) only recommended for **Wireless Presentation**. Connecting the Buttons into a network where the Base Unit is connected by client mode, is not advised for Wireless Conferencing.

A direct Button – Base Unit connection is THE recommended mode of operation for Wireless Conferencing



GO FOR FULL INTEGRATION WITH BUTTON NETWORK INTEGRATION



- Mainly for wireless presentation! (wireless conferencing in preview)
- **Highly secured**, no bridging or pass-through
- Buttons can connect to a corporate wireless network or directly to the Base Unit. For wireless conferencing, a direct Base Unit connection is still advised
- Support for **DFS channels** when integrated into corporate network
- Advised to keep the Access Point of the Base Unit turned on for presence detection of the ClickShare Apps



GENERAL GUIDELINES FOR NETWORK INTEGRATION AND APP BASED CONFERENCING

Direct Button - Base Unit connection is still THE advised setup for Wireless Conferencing!

- When integrating Buttons into the corporate network or using App-based Conferencing:
 - · Client Mode not to be used for Wireless Conferencing (App or Button), this should always go over the LAN
 - · Correct ports should be open!
 - Ensure shortest route in network, reserve enough bandwidth and apply QoS if possible
 - Disable channel switching/hopping, this will cause Button disconnects
 - Keep the Access Point turned ON for APP presence detection
 - The Access Point can be set to hidden with a secret password and on 2.4Ghz to not interfere with corporate Wi-Fi environments
- For App-based Conferencing:
 - Drivers to be installed on a PC with admin rights
 - Up to date ClickShare Desktop App installed (4.13 or higher)
 - To be used with CX Firmware 2.8 or higher.



NETWORK DEPLOYMENT GUIDE

Updated with:

- More recommendations for setup
- Details and requirements for App-based Conferencing and Button network integration
- New information on Miracast capabilities for all CX devices





CS(E) 1.11.1 BUGFIX RELEASE

Bugfix release

- ~10 reported bugs fixed
- Minor Security improvements
- Miracast improvements for CSE-200+



The ClickShare Experience Great things happen when people click

Simple. Easy. Wireless



App-based conferencing



Mobile device audio sharing



Screen sharing via Miracast



Annotation & Blackboarding



Remote sharing of the room display from within your UC&C



Room availability



Broadest range of peripherals



Network integration

Enterprise Grade



ISO 27001 for XMS



XMS Audit logs




XMS: A HIGHLY SECURE PLATFORM

ISO 27k certification




Audit logs



Creates a log of all actions performed by all users on a tenant. Clicking on the action shows additional information.




SMARTCARE INFORMATION AND TENANT INFORMATION CAN NOW BE FOUND IN WEB CONFIGURATOR





IN CASE SMARTCARE HAS NOT YET BEEN CLAIMED, A WARNING WILL BE SHOWN ON THE WEB CONFIGURATOR



Note:

- It can take up to 24 hours for the SmartCare state to be correct!
- Demo and seeding units will not have this information






PERIPHERAL MANAGEMENT

Keep your **peripherals up-to-date**and compatible by installing a **Barco Certified Peripheral Firmware**through the configurator.

The peripheral management functionality is developed in co-operation with our strategic ClickShare Conference partners and will first be available for Logitech Rally devices



The ClickShare Experience Great things happen when people click

Simple. Easy. Wireless.



App-based conferencing



Mobile device audio sharing



Screen sharing via Miracast



Annotation & Blackboarding



Remote sharing of the room display from within your UC&C



Room availability



Broadest range of peripherals



Network integration

Enterprise Grade



ISO 27001 for XMS



XMS Audit logs



ENABLING BRIGHT OUTCOMES

YouTube | youtube.com/BarcoTV

in | linkedin.com/company/Barco

y ∣ twitter.com/Barco

f | facebook.com/Barco